

Deletions in the customer (10.1)


- Customer with kundeid = 70, appeared in delivery 1, was deleted in delivery 2 and reappeared in delivery 3
- Status tracking satellite was used for the customer-hub to track deletions in the data
 - When using the status tracking satellite with the hub table, we can see that the status was set as active (=1) in delivery 1. In delivery 2, the status was set as inactive (=0). In delivery 3, the status was set back as active (=1)
 - If using the current-view of the status tracking satellite, it would return the only the most recent record, where the row is active

```
Just now (1s) 26
1 select
2   hc.business_key,
3   hc.dv_id,
4   stsc.dv_run_id,
5   stsc.status
6 from ddvug_rdv.h_customer hc
7 join ddvug_rdv.sts_customer stsc on hc.dv_id = stsc.dv_id
8 where hc.business_key = 70
9 order by dv_run_id;
> See performance \(1\)
```

	^A _C business_key	^A _C dv_id	^I ₃ dv_run_id	^I ₃ status
1	70	7cbbc409ec990f19c78c75bd1e06f215	1723630854558	1
2	70	7cbbc409ec990f19c78c75bd1e06f215	1723630961825	0
3	70	7cbbc409ec990f19c78c75bd1e06f215	1723631082927	1

Deletions in the customer (10.2)

- Hub-table status tracking satellites are always loaded with ADE's option FULL_EXTRACT, because dv_driving_key and dv_id are always identical
 - Compared to links, where driving_key is used to detect the validity of the relationship



Entities / ddvug_rdv.STS_CUSTOMER / Loads / load_sts_customer_from_stg_kunde_ddvug_webshop_01_db / stg_kunde_ddvug_webshop_to_sts_customer

Summary	Attributes	Physical Opts	Keys	References	Permissions	Loads
ddvug_staging.STG_KUNDE_DDVUG_WEBSHOP						ddvug_rdv.STS_CUSTOMER
1. kundeid		1	\rightarrow DV_HASH	\rightarrow		dv_id
Empty source mapping		0	\rightarrow CURRENT_TS	\rightarrow		dv_load_time
Empty source mapping		0	\rightarrow RUN_ID	\rightarrow		dv_run_id
1. stg_source_system		1		\rightarrow		dv_source_system
1. stg_source_entity		1		\rightarrow		dv_source_entity
Empty source mapping		0	\rightarrow PACKAGE_VERSION	\rightarrow		dv_package_version
Empty source mapping		0	\rightarrow LOAD_NAME	\rightarrow		dv_load_name
1. kundeid		1	\rightarrow DV_HASH	\rightarrow		dv_driving_key
Empty source mapping		0	\rightarrow DV_STATUS	\rightarrow		status

Load options

+ Add load option

Add new load option

OPTION TYPE: OPT_DELTA_EXTRACT

OPTION VALUE (FALSE):

Toggles between DELTA_EXTRACT and FULL_EXTRACT mode.

> Add